

DOOR OPEN LONGER THAN 10 MIN

press ACCEPT on the ALARMS screen to silence the hooter

BLOWER 1

RUNNING

BLOWER 2

RUNNING

HEATER

ON

OVEN DOOR

OPEN

START

STOP

START

STOP

PID DEMAND

CALLING FOR HEAT

DOOR OPEN FOR

12

min

CURE SLOTS

SLOT 1

62%

01:14:22

46 min left

SLOT 2

00:00:00

not loaded

SLOT 3

88%

01:45:10

15 min left

SLOT 4

DONE

02:00:00

ready to unload

SLOT 5

00:00:00

not loaded

SLOT 6

34%

00:41:05

79 min left

ACTIVE ALARMS

3

UNACCOUNTED LOTS

3

SLOTS CURING

3 of 6

CURE TIMERS PAUSED - OVEN NOT FIT TO CURE

high-limit thermostat tripped; timers resume when it is reset

SLOT 1

CURING

01:14:22




remaining 46 min

RESET

SLOT 2

EMPTY

00:00:00



not loaded

START

SLOT 3

CURING

01:45:10



remaining 15 min

RESET

SLOT 4

COMPLETE

02:00:00




ready to unload

RESET

SLOT 5

EMPTY

00:00:00




not loaded

START

SLOT 6

CURING

00:41:05



remaining 79 min

RESET

WHILE THE TIMERS ARE PAUSED

Elapsed time is held, not lost. Each cure still needs its full remaining time once the oven recovers.

EARLY RESET

maintenance only

HOME

SLOTS

COUNTERS

ALARMS

HISTORY

LOGIN

DOOR

OPENED

1 284

CLOSED

1 283

PRODUCTION

LOADED

412

UNLOADED

409

EARLY

3

UNACCOUNTED LOTS

3 loaded - unloaded - still curing
Every unit is a cure cut short with the maintenance passcode.
Each one is in the PLC event log with the slot and how many minutes it was short.

RUNNING HOURS

HEATER

2 841 h

BLOWER 1

3 902 h

BLOWER 2

3 877 h

RESET COUNTERS

quality team only

MOST RECENT EARLY RESETS

06-09 11:47 slot 3 45 min short 04-09 16:02 slot 1 22 min short 02-09 09:35 slot 5 61 min short

HOME

SLOTS

COUNTERS

ALARMS

HISTORY

LOGIN

TIME	ALARM	STATUS
14:21	DOOR OPEN LONGER THAN 10 MIN	ACTIVE
14:19	CURE TIMERS PAUSED - OVEN NOT FIT	ACTIVE
13:58	HIGH-LIMIT THERMOSTAT TRIPPED	ACTIVE
11:04	LOTS LOADED / UNLOADED MISMATCH	ACCEPTED
09:12	BLOWER 2 OVERLOAD TRIPPED	CLEARED
08:47	FAILURE TO REACH SETPOINT	CLEARED

ACCEPT

HISTORY

7 day log

ACTIVE / UNACCEPTED

3 of 14 configured alarms

HOME

SLOTS

COUNTERS

ALARMS

HISTORY

LOGIN

MANUAL TEST ACTIVE - NORMAL INTERLOCKS BYPASSED

exits by itself in 04:12, or when the door opens

BLOWER 1

PRESS AND HOLD

runs only while touched



contactor feedback
not confirmed

BLOWER 2

PRESS AND HOLD

runs only while touched



contactor feedback
not confirmed

HEATER

PRESS AND HOLD

runs only while touched



contactor feedback
not confirmed

CONDITIONS REQUIRED

- E-stop released
- door closed
- no overload tripped
- high-limit healthy
- no cure running

EXIT MANUAL TEST

HOME

SLOTS

COUNTERS

ALARMS

HISTORY

LOGIN


TIMINGS

Heat-up watchdog	60	min	10 - 240
Door watchdog	600	s	60 - 1800
Chatter transitions	8		4 - 50
Chatter window	10	s	5 - 60
Heater minimum ON	20	s	5 - 120
Heater minimum OFF	20	s	5 - 120
Manual test timeout	300	s	60 - 900
Auto-logout	300	s	60 - 900
Cure time	7200	s	fixed at 2 h

OPTIONS



Cure timers pause on a fault



Heater requires airflow

PASSCODES

Change both from the shipped defaults before handover.

MAINTENANCE

QUALITY

Quality's code is changed by quality, on their own login.

PASSCODE

* * * *

1	2	3
4	5	6
7	8	9
CLR	0	DEL

LOG IN AS

MAINTENANCE
early reset - manual test - settings

QUALITY
resetting the counters

LOCKED OUT
247 seconds remaining - 3 wrong entries

LOG OUT

AUTO-LOGOUT
after 5 minutes idle

TWO SEPARATE PASSCODES - NEITHER ROLE CAN DO THE OTHER'S JOB
Maintenance cuts a cure short; quality, and only quality, clears the counters that record it.

THIS ENDS A CURE BEFORE ITS 2 HOURS ARE UP

it is recorded against your login with the slot and the minutes remaining, and it does NOT count as a lot unloaded

SLOT 1	01:14:22	46 min remaining	EARLY RESET
SLOT 2	-	not loaded	
SLOT 3	01:45:10	15 min remaining	EARLY RESET
SLOT 4	02:00:00	complete - use the normal reset	
SLOT 5	-	not loaded	
SLOT 6	00:41:05	79 min remaining	EARLY RESET

RESETTING A COUNTER CLEARS THE PRODUCTION RECORD

take the readings first; the reset itself is written to the 7 day log

DOOR COUNTERS

opened1 284

closed1 283

RESET

LOT COUNTERS

loaded412

unloaded409

early resets3

RESET

WHY ONLY QUALITY CAN DO THIS

Maintenance is who cuts a cure short with an early reset. If the maintenance passcode could also clear these counters, the person who ended a cure early could erase the record of having done it. The two passcodes are held in the PLC, not in this panel, so replacing the HMI does not change the rule.

DATE	TIME	EVENT	DETAIL
06-09	14:21	Door open longer than 10 min	600 s
06-09	13:58	Cure timers paused	3 slots
06-09	11:47	Slot 3 EARLY RESET	45 min short
06-09	11:46	MAINTENANCE logged in	
06-09	10:12	Slot 1 reached 2 h	
06-09	08:12	Slot 1 started	
05-09	17:44	Failed login attempt	attempt 2

EXPORT TO USB

this panel's alarm history, as CSV

RETENTION

This panel keeps the alarm history. The full 7 day event log - every slot start, early reset, login and counter reset - is written to the SD card in the PLC, not here.